

# Iowa Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

## Introduction

This technical note is designed to help conservation planners address pest management concerns in the conservation planning process.

NRCS Pest Management Policy states that we have four roles in pest management:

- (1) Evaluate environmental risks associated with a client's probable pest suppression strategies.
- (2) Provide technical assistance to clients to mitigate identified environmental risks.
- (3) Assist clients to adopt IPM techniques that protect natural resources.
- (4) Assist clients to:
  - (i) Inventory, assess, and suppress noxious and invasive weeds on non-cropland.
  - (ii) Suppress weeds to ensure successful implementation and/or maintenance of permanent vegetative conservation practices (e.g., buffer type practices).

Roles 1, 2 and 3 are addressed in the conservation planning process with the application of **Integrated Pest Management (IPM) (Code 595)** and other conservation practices. Even though NRCS does not provide technical assistance for managing pests on cropland, NRCS can work with Extension, producers and their crop consultants to integrate IPM into the conservation planning process to prevent and/or mitigate pest management environmental risks.

Integrated Pest Management (IPM) (Code 595) is designed to support the adoption of a comprehensive IPM system: a site-specific combination of pest Prevention, Avoidance, Monitoring, and Suppression strategies, or IPM „PAMS‘ strategies.

The two primary goals of the 595 standard are to prevent environmental risks if possible and then

to mitigate environmental risks that cannot be prevented.

A comprehensive IPM system prevents and avoids *pests* as much as possible to reduce the need for *pest suppression*, including the use of hazardous pesticides.

A comprehensive IPM system also includes carefully monitoring pest populations and only utilizing suppression techniques when the economic benefit is greater than the cost. These economic pest thresholds must be developed for each pest in each cropping system based on the biology of the crop, the pest, and the pest's natural enemies. The economic threshold is then dynamically adjusted based on the cost of the pest suppression technique and the projected value of the crop.

A comprehensive IPM system also includes carefully managing the use of different pest suppression techniques to delay the onset of pest resistance to each suppression technique. Utilizing a combination of different techniques including pesticides with different modes of action is critical to maintaining their efficacy.

And finally, a comprehensive IPM system must also mitigate environmental risks that cannot be prevented by utilizing appropriate IPM techniques that minimize risks to non-target species in the field and reduce off-site movement of hazardous pesticides.

In some cropping systems a comprehensive IPM system will not be feasible because appropriate IPM technology has not been developed. **The 595 standard can be used to support the application of individual IPM techniques if they appropriately mitigate site-specific pest suppression risks to natural resources and/or humans.**

NOTE: Identified risks associated with planned pest suppression can also be addressed through other conservation practices or a system of conservation practices that includes 595.

Role 4 in our Pest Management Policy is addressed in the conservation planning process with the application of **Brush/Shrub Control**

(Code 314) and **Herbaceous Weed Control (Code 315)** on non-cropland to address natural resource concerns related to plant pests, including invasive, noxious and prohibited plants. **Integrated Pest Management (IPM) (Code 595) should be used to prevent and/or mitigate pest management environmental risks associated with the application of 314 and 315.**

### **NRCS Pesticide Risk Analysis in the Conservation Planning Process**

NRCS utilizes the Windows Pesticide Screening Tool (WIN-PST) for water quality pesticide risk analysis. **NRCS uses WIN-PST to identify sensitive soil/pesticide combinations and what type of mitigation will help protect site-specific natural resources.**

### **Utilizing WIN-PST in the Conservation Planning Process**

WIN-PST is the NRCS supported technical tool that is used to assess relative pesticide leaching, solution runoff, and adsorbed runoff risk to water quality. WIN-PST analysis is based on:

- Soil properties
- Pesticide physical properties
- Pesticide toxicity data

The major components of the NRCS non-point source water quality pesticide risk analysis are:

1. The potential for pesticide loss in
  - water that leaches below the rootzone;
  - water that runs off the edge of the field;
  - sediment that leaves the field in run off;
2. Chronic (long term) pesticide toxicity to human drinking water and aquatic habitat;
3. And finally, the combination of pesticide loss potential with pesticide toxicity to provide site-specific ratings for pesticide hazards in leaching, solution runoff, and sediment adsorbed runoff.

### The final ratings are called **WIN-PST Soil/Pesticide Interaction Hazard Ratings**.

The term “hazard” is used even though these ratings include both pesticide toxicity and a partial exposure analysis based on field conditions. It is the responsibility of the planner to put these hazard ratings into proper context by using their professional judgment to assess

the potential for pesticide movement below the bottom of the rootzone and beyond the edge of the field to identified ground or surface water resources, as well as the potential for that pesticide contamination to impact the water resources based on watershed and water body characteristics. This entire process is considered a “risk” analysis, so the term “hazard” is used in the final WIN-PST ratings to remind users that they must put these “partial” ratings into the proper context to fully analyze risk to human drinking water and aquatic habitat.

WIN-PST provides ratings for 5 different categories of resource concerns:

- **‘Human Hazard Leaching’** for leaching risk to drinking water
- **‘Fish Hazard Leaching’** for leaching risk to aquatic habitat (lateral flow to streams)
- **‘Human Hazard Solution’** for solution runoff risk to drinking water
- **‘Fish Hazard Solution’** for solution runoff risk to aquatic habitat
- **‘Fish Hazard Adsorbed’** for adsorbed runoff risk to aquatic habitat including benthic organisms.

Note: there is no WIN-PST rating for ‘Human Hazard Adsorbed’ since human exposure to sediment is minimal.

The final “WIN-PST Soil/Pesticide Interaction Hazard Ratings” are **‘Very Low’**, **‘Low’**, **‘Intermediate’**, **‘High’** or **‘Extra High’**.

To fully analyze the risk of a pesticide to a human drinking water supply or aquatic habitat, the user must consider the impact of flow path characteristics between the field and the water body of concern (through the vadose zone to groundwater or overland flow to surface water); watershed characteristics; and water body characteristics.

On the higher end of the overall risk spectrum, the flow path from the field to the water body will be short and direct with little opportunity for pesticide degradation or assimilation; the watershed will have significant pesticide loading potential from numerous fields that are managed in a similar fashion as the field being analyzed; and the water body will be sensitive to pesticide contamination due to limited flushing and dilution.

On the lower end of the overall risk spectrum, the flow path to the water body will be long and

arduous with lots of opportunity for pesticide degradation and assimilation; the watershed will have only a few fields that are managed in a similar fashion so there will be limited loading potential for the pesticide in question; and the water body will not be very sensitive to pesticide contamination due to lots of flushing and dilution.

If the overall risk is low, the conservation planner will not identify a water quality concern related to the use of pesticides, so no mitigation will be needed. If the overall risk is high, a suite of conservation practices may be required to provide enough mitigation to meet eFOTG quality criteria. Appropriate mitigation should be chosen based on final WIN-PST hazard ratings for applicable pesticide loss pathways to identified water resource concerns.

To conduct a WIN-PST analysis:

1. Choose all the major soil types that cover 10% or more of the field or planning area
2. Choose all the pesticides that the client is planning to use  
(Note that each pesticide can be chosen by product name, EPA registration number, or active ingredient name, but the final ratings are specific to each active ingredient)
3. Analyze the results for each soil/pesticide interaction
4. **Select the highest hazard soil/pesticide combination for the identified natural resource concern(s) to plan appropriate mitigation**

In the example below, there is a solution runoff concern to aquatic habitat. Pesticides X and Y are planned for a field that contains Soils A, B and C.

Soil/Pesticide Combination	WIN-PST Fish Hazard Solution Rating
Soil A - Pesticide X (20% of the area)	Very Low
Soil B - Pesticide X (50% of the area)	Low
Soil C - Pesticide X (25% of the area)	Intermediate
Soil A - Pesticide Y (20% of the area)	Low
Soil B - Pesticide Y (50% of the area)	Intermediate
<b>Soil C - Pesticide Y (25% of the area)</b>	<b>High</b>

In this example, the “High” rating for the combination of Soil C with Pesticide Y would be selected to plan an appropriate level of mitigation to protect the aquatic habitat.

**Applying the Integrated Pest Management (IPM) (Code 595) Standard**

If a conservation planner identifies natural resource concerns related to pest management activities, 595 may be applied to address those concerns.

**If a pesticide related water resource concern is identified, the 595 standard requires a specific level of mitigation based on WIN-PST results.**

For identified water quality concerns related to pesticide leaching, solution runoff and adsorbed runoff, WIN-PST must be used to evaluate potential hazards to humans and/or fish as appropriate, for each pesticide to be used. The minimum level of mitigation required for each resource concern is based on the final “WIN-PST Soil/Pesticide Interaction Hazard Ratings” Table below:

WIN-PST Identified Final Hazard Rating	Minimum Mitigation Index Score Level Needed
Low or Very Low	None Needed
Intermediate	20
High	40
Extra High	60 or more

**Mitigation requirements can be met with IPM techniques and/or conservation practices.** See Table I at the end of this technical note for mitigation index values for IPM techniques and Table II for mitigation index values for conservation practices. The index values from Table I can be added to the index values from Table II to calculate the total index score for the planned conservation system.

For example, if “Fish Hazard Solution” is identified as a pathway of concern for an identified water resource and WIN-PST reports an „Intermediate’ rating, IPM techniques from Table I or conservation practices from Table II that address solution runoff must be applied so that the sum of the index values from either table in the „Solution Runoff’ column for the selected IPM mitigation techniques and conservation practices will be 20 or more. Similarly, a „High’ rating would require a sum of 40 or more, and an „Extra High’ rating would require a sum of 60 or more. This will be the case for all natural resource concerns and all applicable pesticide loss pathways identified by the conservation planner with the aid of WIN-PST.

As an alternative to mitigation, the conservation planner can work with Extension personnel,

published Extension recommendations, the producer or their crop consultant to see if there are lower risk alternatives that still meet the producer’s objectives. *A producer can choose to use a pesticide that has risk if they also apply appropriate mitigation, or they can substitute a low risk pesticide that needs no mitigation – pesticide choice is the producer’s decision.*

**Pesticide drift** has also been identified as a major pesticide loss pathway. **Note that drift can be a major pesticide loss pathway to surface water in some cases.** *Appropriate mitigation for drift may be required in addition to mitigation for leaching, solution and adsorbed pesticide loss pathways in order to adequately protect a surface water resource.*

Predicting spray drift is very difficult because it is influenced by many rapidly changing site-specific factors including wind speed, relative humidity, temperature and the presence of temperature inversions. Spray droplet size as determined by nozzle configuration and pressure also plays an important role in spray drift.

**If the conservation planner identifies a natural resource concern related to pesticide spray drift, the minimum level of mitigation required is an index score of 20.** The index values from Table I can be added to the index values from Table II to calculate the total index score for the planned conservation system.

**Pesticide Volatilization** has been identified as a contributor to air quality concerns through Volatile Organic Compound (VOC) emissions that are a key precursor to ground-level ozone.

Pesticide related VOC emissions are influenced by the vapor pressure the active ingredient and the way the pesticide product is formulated. Emulsifiable concentrates have higher VOC emissions than other formulations. If the conservation planner identifies a VOC related natural resource concern, one or more of the following VOC mitigation techniques must be applied:

1. Use lower VOC emitting pesticide formulations - specifically eliminating the use of emulsifiable concentrates when other formulations are available;
2. Use precision pesticide application or “Smart Sprayer” technology including:

## Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

- Near-infrared-based weed sensing systems
  - Map/GPS-based variable rate application
  - Sonar-based vegetation sensors
  - Computer controlled spray nozzles
  - Hoods and shields to direct applications
  - Wicks
  - Backpacks
  - Remote sensing, GIS, or other spatial information system
  - Steam desiccation systems
  - Fumigant delivery with precision application
  - Fumigant delivery with drip irrigation
  - Fumigant soil retention using precision water application;
3. Use impermeable tarps to cover fumigated areas;
  4. Shift dates of fumigant application to outside the May - October timeframe to move VOC emissions out of the non-attainment period;
  5. Use solarization (e.g. irrigate and tarp during summer fallow to kill pests without fumigation;
  6. Use biofumigants or other soil treatments (e.g. thiosulfate) instead of pesticides.
  7. Fallow fields for several years before replanting an orchard crop or inoculate young trees (e.g. with yeast) to reduce fumigant use;

**Pesticide Direct Contact** can affect pollinators and other beneficial species while pesticides are being applied and later when pollinators and other beneficial species reenter the treated area. This direct exposure to pesticides can occur even when spray drift is minimized.

For more information, see *How to Reduce Bee Poisoning from Pesticides* available at: <http://extension.oregonstate.edu/catalog/pdf/pnw/pnw591.pdf>

If the conservation planner identifies a pesticide direct contact concern to pollinators and other beneficial species, choose two or more of the following mitigation techniques:

1. Time pesticide applications when pollinators are least active (e.g. at night or when temperatures are low.) Note that dewy nights may cause an insecticide to remain wet on the foliage and be more toxic to bees the following morning, so exercise caution;
2. Time pesticide applications when crops are not in bloom and keep fields weed free to discourage pollinators from venturing into the crop;
3. Use pesticides that are less toxic to pollinators and beneficial species. Note: all pesticide recommendations must come from Extension or an appropriately certified crop consultant.
4. Use selective insecticides that target a narrow range of insects (e.g. *Bacillus thuringiensis* (Bt) for moth caterpillars) to reduce harm to beneficial insects like bees;
5. Use liquid formulations instead of dusts and fine powders that may become trapped in the pollen collecting hairs of bees and consequently fed to developing larvae;
6. Use alternatives to insecticides such as pheromones for mating disruption and kaolin clay barriers for fruit crops;

**Cultural and mechanical pest management techniques** can cause natural resource degradation. For example, burning for weed control can cause air pollution and tillage for weed control can cause soil erosion. All natural resource concerns from all forms of pest management should be evaluated, and significant natural resource concerns should be addressed to eFOTG quality criteria levels.

### Developing the IPM Plan

IPM elements and guidelines from Iowa State University Extension should be utilized where available. A national listing is available at: <http://www.ipmcenters.org/ipmelements/index.cfm>. The goal is to develop an efficient IPM system that uses prevention, avoidance, monitoring, and then finally judicious suppression when a pest population exceeds an economic threshold. **IPM helps assure that unnecessary environmental risks are avoided.**

The best way to develop a good IPM system is to consider economics, efficacy, and environmental risk all at the same time.

Developing an IPM plan for a producer as part of the conservation planning process will allow the

**February 2011**

IPM Plan to directly address identified natural resource concerns as well as provide a broader context to area-wide pest management considerations and habitat management for beneficial species.

It is important to note that other conservation practices like Crop Rotation, Cover Crop, and Field Borders can also be used to develop an efficient IPM system. And additional conservation practices like Filter Strips and Residue Management can be used in the conservation system along with the 595 conservation practice to provide adequate mitigation.

The IPM mitigation techniques in Table I below are included in most Land Grant University IPM Programs, but we have to be careful because NRCS cannot make pesticide recommendations ourselves.

*We must be certain that Extension or an appropriately certified farm advisor supports and recommends the use of these techniques, because changing the way a pesticide is applied or substituting a different pesticide is making a pesticide recommendation, and that is not supported by NRCS Pest Management Policy. However, **NRCS can and should fully support the conservation benefits of these IPM mitigation techniques.***

**Using Table I - IPM Techniques for Reducing Pesticide Environmental Risk and Table II - Conservation Practices for Reducing Pesticide Environmental Risk**

Table I identifies IPM techniques and Table II identifies conservation practices that have the potential to prevent or mitigate pesticide impacts on water and air quality. Water quality is addressed through four separate pesticide loss pathways: leaching, solution runoff, adsorbed runoff, and drift. The pesticide drift pathway also applies to air quality.

Not all IPM techniques and conservation practices will be applicable to a given situation. Relative effectiveness ratings by pesticide loss pathway are indicated with an index value of 5, 10, or 15. The tables also identify how the IPM techniques and conservation practices function and the performance level that the index value is based on. Effectiveness of any IPM technique or conservation practice can be highly variable based on site conditions and how it is designed and maintained. The professional judgment of the planner will ultimately determine the

Page 6 of 13

effectiveness of a particular IPM technique or conservation practice for a particular field or planning area.

Tables I and II are based on available research specific to IPM technique or conservation practice, related research, and the best professional judgment of NRCS technical specialists. The ratings are relative index values as opposed to absolute values, much like the Conservation Practice Physical Effects (CPPE) matrix ratings. The index values are intended to help planners choose the best combination IPM techniques and conservation practices for their identified resource concerns. The ratings are based on the relative *potential* for IPM techniques or conservation practices to provide mitigation. The IPM techniques or conservation practices need to be specifically designed, implemented and maintained for the mitigation potential to be realized. Varying site conditions can influence mitigation effectiveness, but the relative index values indicate which conservation practices or IPM mitigation techniques will generally provide more or less mitigation under a given set of conditions.

A general rule of thumb for IPM techniques or conservation practices having an index value of 5 is that they generally have the potential to reduce losses by 10 -15%. IPM techniques or conservation practices having an index value of 10 generally have the potential to reduce losses by about 25%, and IPM techniques or conservation practices having an index value 15 generally have the potential to reduce losses by 50% or more.

The original reference for many of the ratings in Tables I & II is: *Aquatic Dialogue Group: Pesticide Risk Assessment and Mitigation, Baker JL, Barefoot AC, Beasley LE, Burns LA, Caulkins PP, Clark JE, Feulner RL, Giesy JP, Graney RL, Griggs RH, Jacoby HM, Laskowski DA, Maciorowski AF, Mihaich EM, Nelson Jr HP, Parrish PR, Siefert RE, Solomon KR, van der Schalie WH, editors. 1994. Society of Environmental Toxicology and Chemistry, Pensacola, FL., pages 99-111 and Table 4-2.* This reference provides ranges of effectiveness for various mitigation techniques.

**Table I – IPM Techniques for Reducing Pesticide Environmental Risk**

IPM Techniques <sup>1</sup>	Mitigation Index Value <sup>4</sup> (by Pesticide Loss Pathway)				Function and Performance Criteria
	Leaching	Solution Runoff	Adsorbed Runoff	Drift	
Application Timing - Ambient Temperature				5	Reduces exposure - spraying during cooler temperatures (e.g. early morning, evening or at night) can help reduce drift losses. Avoid spraying in temperatures above 90° F.
Application Timing - Rain	15	15	15		Reduces exposure - delaying application when significant rainfall events are forecast that could produce substantial leaching or runoff can reduce pesticide transport to ground and surface water.
Application Timing - Relative Humidity				5	Reduces exposure - spraying when there is higher relative humidity reduces evaporation of water from spray droplets thus reducing drift losses.
Application Timing - Wind				10	Reduces exposure - delaying application when wind speed is not optimal can reduce pesticide drift. Optimal spray conditions for reducing drift occur when the air is slightly unstable with a very mild steady wind between 2 and 9mph.
Formulations and Adjuvants <sup>2,3</sup>	5	5	5	5	Reduces exposure – specific pesticide formulations and/or adjuvants can increase efficacy and allow lower application rates, drift retardant adjuvants can reduce pesticide spray drift.
Monitoring + Economic Pest Thresholds.	15	15	15	15	Reduces exposure - reduces the amount of pesticide applied with preventative treatments because applications are based on monitoring that determines when a pest population exceeds a previously determined economic threshold.
Partial Treatment	15	15	15	10	Reduces exposure - spot treatment, banding and directed spraying reduces amount of pesticide applied. Assumes less than 50% of the area is treated.

Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

Precision Application Using “Smart Sprayers”	10	10	10	10	Reduces exposure - using “Smart Sprayer” technology (i.e. green sensors, sonar-based sensors, GPS-based variable rate application, computer controlled spray nozzles, etc.) can substantially reduce the amount of pesticide applied.
Set-backs	5	5	5	10	Reduces exposure – reduces overall amount of pesticide applied, reduces offsite pesticide drift. Assumes that the set-backs with no application are at least 30 feet wide.
Soil Incorporation <sup>2,3</sup>		15	15		Reduces exposure – reduces solution and adsorbed runoff losses, but potentially increases leaching losses, especially for low K <sub>OC</sub> pesticides. Applicable to shallow mechanical or irrigation incorporation. Not applicable if pesticide leaching to groundwater is an identified natural resource concern. Not applicable if soil erosion is not adequately managed.
Spray Nozzle Selection, Maintenance and Operation.				10	Reduces exposure – selecting appropriate nozzle and pressure for the application, with an emphasis on higher volume spray nozzles run at lower pressures, will produce larger droplets and a narrower droplet size distribution, which reduces spray drift. Proper nozzle spacing, boom height, and boom suspension, along with frequent calibration and replacement of worn nozzles and leaking tubing, can increase efficacy and reduce drift potential.
Substitution – Cultural, Mechanical or Biological Controls	15	15	15	15	Reduces risk - substituting alternative cultural, mechanical or biological pest suppression techniques to reduce the application of a pesticide that poses a hazard to an identified natural resource concern. Not applicable if hazards from alternative suppression techniques are not adequately managed.
Substitution – Lower Risk Pesticides <sup>2,3</sup>	15	15	15	15	Reduces risk - substituting an alternative lower risk pesticide to reduce the application of a pesticide that poses a hazard to an identified natural resource concern. Not applicable if the alternative pesticide is not explicitly recommended by Extension or an appropriately certified crop consultant because NRCS cannot make pesticide recommendations.
Substitution - Semiochemicals	15	15	15	15	Reduces risk – using semiochemicals (e.g., mating disrupting pheromones) to decrease reproductive success or control population density/location to reduce pesticide applications.

## Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

<sup>1</sup>Additional information on pest management mitigation techniques can be obtained from Extension pest management publications including IPM Guidelines and Crop Profiles, pest management consultants, and pesticide labels.

<sup>2</sup>The pesticide label is the law - all pesticide label specifications must be carefully followed, including required mitigation. Additional mitigation may be required for NRCS identified natural resource concerns.

<sup>3</sup>NRCS does not make pesticide recommendations. All pesticide application techniques must be recommended by Extension or an appropriately certified crop consultant and selected by the producer.

<sup>4</sup>Numbers in these columns represent index values that indicate relative effectiveness of IPM mitigation techniques to reduce hazardous pesticide losses through the identified pathways.

**Table II – Conservation Practices for Reducing Pesticide Environmental Risk**

Pesticide Mitigation Conservation Practices <sup>1,2</sup>	Mitigation Index Value <sup>4</sup> (by Pesticide Loss Pathway)				Function and Performance Criteria
	Leaching	Solution Runoff	Adsorbed Runoff	Drift	
Bedding (310)	5	5	5		Increases surface infiltration and aerobic pesticide degradation in the rootzone.
Conservation Cover (327)	10	10	10		Increases infiltration, reduces soil erosion, and builds soil organic matter In perennial cropping systems such as orchards, vineyards, berries and nursery stock.
Conservation Crop Rotation (328)	10	10	10		Reduces the need for pesticides by breaking pest lifecycles. The rotation shall consist of at least 2 crops in the rotation and no crop grown more than once before growing a different crop.
Constructed Wetland (656)	5	5	10		Captures pesticide residues and facilitates their degradation.
Contour Buffer Strips (332)		10	10		Increases infiltration, reduces soil erosion.
Contour Farming (330)		5	5		Increases infiltration and deep percolation, reduces soil erosion.
Cover Crop (340) that is incorporated into the soil.	5	5	5		Increases infiltration, reduces soil erosion, builds soil organic matter. Assumes at least 4000 lbs/ac of live biomass at the time of tillage.
Cover Crop (340) for weed suppression that is mulch tilled or no-tilled into for the next crop.	10	10	10	10	Increases infiltration, reduces soil erosion, builds soil organic matter. Assumes at least 4000 lbs/ac of live biomass at the time of tillage and at least 30% ground cover at the time of the pesticide application.
Cross Wind Trap Strips (589C)			10 <sup>3/</sup>		Reduces wind erosion and adsorbed pesticide deposition in surface water, traps adsorbed pesticides.
Dike (356)		10	10		Reduces exposure potential - excludes outside water or captures pesticide residues and facilitates their degradation. Not applicable if pesticide leaching to groundwater is an identified natural resource concern.

Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

Pesticide Mitigation Conservation Practices <sup>1,2</sup>	Mitigation Index Value <sup>4</sup> (by Pesticide Loss Pathway)				Function and Performance Criteria
	Leaching	Solution Runoff	Adsorbed Runoff	Drift	
Drainage Water Management (554)		10	10		Drainage during the growing season increases infiltration and aerobic pesticide degradation in the rootzone and reduces storm water runoff. Managed drainage mode when the field is not being cropped reduces discharge of pesticide residues from the previous growing season. Seasonal saturation may reduce the need for pesticides. Not applicable if pesticide leaching to groundwater is an identified natural resource concern.
Field Border (386)		5	10	5	Increases infiltration and traps adsorbed pesticides, often reduces application area resulting in less pesticide applied, can provide habitat for beneficial insects which reduces the need for pesticides, can provide habitat to congregate pests which can result in reduced pesticide application, also can reduce inadvertent pesticide application and drift to surface water. Assumes 20 foot minimum width.
Filter Strip (393)		10	15	10	Increases infiltration and traps adsorbed pesticides, often reduces application area resulting in less pesticide applied, can provide habitat for beneficial insects which reduces the need for pesticides, can provide habitat to congregate pests which can result in reduced pesticide application, also can reduce inadvertent pesticide application and drift to surface water. Assumes 30 foot minimum width.
Forage Harvest Management (511)	10	10	10	10	Reduces exposure potential - timely harvesting reduces the need for pesticides.
Hedgerow Planting (442)			10 <sup>3/</sup>	10	Reduces adsorbed pesticide deposition in surface water, also can reduce inadvertent pesticide application and drift to surface water
Irrigation System, Sprinkler (442)	10	10	10		Reduces exposure potential - efficient and uniform irrigation reduces pesticide transport to ground and surface water.
Irrigation Water Management (449)	15	15	15		Reduces exposure potential - water is applied at rates that minimize pesticide transport to ground and surface water, promotes healthy plants which can better tolerate pests.

Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

Pesticide Mitigation Conservation Practices <sup>1,2</sup>	Mitigation Index Value <sup>4</sup> (by Pesticide Loss Pathway)				Function and Performance Criteria
	Leaching	Solution Runoff	Adsorbed Runoff	Drift	
Mulching (484) with natural materials	10	10	10		Increases infiltration, reduces soil erosion, reduces the need for pesticides.
Mulching (484) with plastic	10	5	5		Reduces the need for pesticides. Not applicable if erosion and pesticide runoff from non-mulched areas is not adequately managed.
Residue Management, No-till and Strip-Till (329)	5	10	15		Increases infiltration, reduces soil erosion, builds soil organic matter. Assumes at least 60% ground cover at the time of application.
Residue Management, Mulch-Till (345)	5	5	10		Increases infiltration, reduces soil erosion, builds soil organic matter. Assumes at least 30% ground cover at the time of application.
Residue Management, Ridge Till (346)	5	5	10		Increases infiltration, reduces soil erosion, builds soil organic matter.
Riparian Forest Buffer (391)	5	15	15	10	Increases infiltration and uptake of subsurface water, traps sediment, builds soil organic matter, and reduces pesticide drift. This assumes 30 foot minimum width.
Riparian Herbaceous Cover (390)	5	10	10	5	Increases infiltration, traps sediment, builds soil organic matter, and reduces pesticide drift. This assumes 30 foot minimum width.
Sediment Basin (350)			10		Captures pesticide residues and facilitates their degradation. Not applicable if less than 50% of the treatment area drains into the sediment basin.
Stripcropping (585)		15	15	5	Increases infiltration, reduces soil erosion and generally will only be treating half the area of concern.
Subsurface Drainage (606)	5	10	10		Increases infiltration and aerobic pesticide degradation in the root zone. *Note – avoid direct outlets to surface water
Terrace (600)		10	15		Increases infiltration and deep percolation, reduces soil erosion. Not applicable if pesticide leaching to groundwater is an identified natural resource concern.

Agronomy Technical Note 37: Pest Management in the Conservation Planning Process

Pesticide Mitigation Conservation Practices <sup>1,2</sup>	Mitigation Index Value <sup>4</sup> (by Pesticide Loss Pathway)				Function and Performance Criteria
	Leaching	Solution Runoff	Adsorbed Runoff	Drift	
Water and Sediment Control Basin (638)		10	15		Captures pesticide residues and facilitates their degradation, increases infiltration and deep percolation. Not applicable if pesticide leaching to groundwater is an identified natural resource concern.
Windbreak/Shelterbelt Establishment (380)			10 <sup>3/</sup>	10	Reduces wind erosion, reduces adsorbed pesticide deposition in surface water, traps adsorbed pesticides, and reduces pesticide drift.

<sup>1/</sup> Additional information on pest management mitigation techniques can be obtained from Extension pest management publications including IPM Guidelines and Crop Profiles, pest management consultants, and pesticide labels.

<sup>2/</sup> The pesticide label is the law - all pesticide label specifications must be carefully followed, including required mitigation. Additional mitigation may be needed to meet NRCS pest management requirements for identified resource concerns.

<sup>3/</sup> Mitigation applies to adsorbed pesticide losses being carried to surface water by wind.

<sup>4/</sup> Numbers in these columns represent index values that indicate relative effectiveness of pesticide mitigation techniques to reduce hazardous pesticide losses through the identified pathways.