

Installation Guide

noCCE-WinPond 1.5 REL3

Place the WinPond files on a Workstation Hard Drive or USB Device.

This section will establish the WinPond 1.5 REL3 software in the XP directory of the Workstation Hard Drive or USB Device.


Note: Before attempting to install WinPond 1.5 REL3, you must first have Microsoft .NET 1.1 Framework installed and present on your computer. WinPond 1.5 REL3 is compatible with Microsoft .Net 2.0 Framework installed on the computer.

Note: WinPond 1.5 REL3 is configured to run on USDA CCE configured Windows XP computer systems. There is no guarantee that WinPond 1.5 REL3 will operate on any computer that does not conform to USDA CCE configured Windows XP computer systems.


Extract WinPond 1.5 REL3 Files to a Location on Hard Drive or USB Device.

1. Download the **WinPond1.5REL3_PKG.zip** file to your hard drive.
2. Browse to **WinPond1.5REL3_PKG.zip** open the zip file and extract the two included files to C:\temp
3. Click on **[Start] [Run] [Browse]** to C:/temp
4. Double click on **WinPond1.5REL3.exe** then click on **[OK]**. A Messenger Service window will open stating "No drives were found containing the XPWorkStationShare. Continuing with the install routine." Click on **[OK]**
5. This window will open.

Ignore this window.




This window will open.




6. Change the "Save Files in Folder" field to C: (or the Drive letter of the USB device) then click on **[Next]**.
7. When completed, click on **[Finish]** in the InstallShield Wizard Complete window.

Installation of WinPond 1.5 REL3

1. Log in with an account that has administrative privileges.
2. Click **[Start]** **[Run]** then **[Browse]** or type in:
3. **[Drive]:\XP\NRCs\WinPond\client\1.5.2405.11111\pkg**
4. Double click on **[winpond_setup]**.
5. A DOS window will appear and run several scripts automatically. Then the Welcome screen will appear.



6. Click **[Next]**
The Setup Status window will appear.
7. Once the software is installed, the InstallShield Wizard Complete screen will appear.



8. Click **[Finish]**
The Final WinPond Options window will appear



9. Click **[Finish]**
The program is installed on the workstation. It can be accessed by clicking on

- [Start] [All Programs] [Engineering Applications] [WinPond] [WinPond]
10. You may safely delete the all files in
[Drive]:\XP\NRCs\WinPond\client\1.5.2405.11111


WinPond 1.5REL3 Required Program Setup

Review WinPond Help before attempting to use WinPond, especially

1. Section X Introduction, 3. Create a “Job Approval.st” file
2. Section X Introduction, 4. Set Defaults

Uninstalling WinPond 1.5 REL3

1. Log in with an account that has administrative privileges to complete these tasks.
2. Click on [Start] [Control Panel] [Add or Remove Programs]
3. Select WinPond then click on [Change/Remove]
4. At the Welcome screen, make sure the radio button next to Remove is selected, then click [Next]



5. At the “Maintenance Complete” screen, click [Finish]
6. Close the Add or Remove Program window.